


APPENDIX



Steps to execute the program in a personal computer with the 64-bit Windows 7 or later operating system.

- 1) Click **Start** button and type **cmd.exe** in the *Search programs and files* box.
- 2) Select **cmd** and press right mouse button.
- 3) Click **Run as administrator** option.
- 4) A windows appears on screen showing “Do you want to allow the following program to make changes to this computer?”. In this windows, click **Yes** button.
- 5) A black screen appears on screen starting with the **C:\Windows\system32>**- command. In here, type **regsvr32 /u “C:\Program Files (x86)\WinPyrox\MSFLXGRD.OCX** and,
- 6) Press **ENTER** key.
- 7) You will see a windows on screen showing “*DllUnregisterServer in C:\Program Files (x86)\WinPyrox\MSFLXGRD.OCX succeeded*”. Press **OK** button to continue.
- 8) Type **regsvr32 “C:\Program Files (x86)\WinPyrox\MSFLXGRD.OCX** and,
- 9) Press **ENTER** key.
- 10) You will see a windows on screen showing “*DllRegisterServer in C:\Program Files (x86)\WinPyrox\MSFLXGRD.OCX succeeded*”. Press **OK** button to continue.
- 11) Finally, click **WinPyrox** icon on desktop to execute the program.